

autoSHARP reference card	
set up	
Set up for csh or tcsh	<code>source /some/where/SHARP/installed/setup.csh</code>
Set up for bash, ksh, zsh, or sh	<code>./some/where/SHARP/installed/setup.sh</code>
Input file information	
Sequence file format (*.pir)	>1022 MGSDKIHHHHHMLMDILEILYYKKGKEFGILEKKMKEIFNETGVSLEPVNSEL IGRIFLKI SVLEEGEEVPSFAIKALTPKENAVDLPLGDWTDLKNVVEEIDYLD YGDMKILSEKNWYKIYVPYSSVKKKNRNELVVEEFMKYFFESKGWNPGEYTFVQ IDNLF *
Reflection file format	SCALEPACK (*.sca) or MTZ (*.mtz), e.g. from autoPROC
Known heavy-atom positions (fractional coordinates)	ATOM Se 0.7050 -0.1857 -0.0639 ATOM Se 0.4613 0.4419 0.0687 ATOM Se 0.7190 0.1720 -0.2294 ATOM Se 0.7287 0.2058 -0.2216
autoSHARP: most useful options	
Brief help message	<code>run_autoSHARP.sh -h</code>
Describe (unique) content of asymmetric unit	<code>run_autoSHARP.sh -seq <file.pir></code> - or - <code>run_autoSHARP.sh -nres <# residues></code>
Give space group instead of reading from reflection file(s)	<code>run_autoSHARP.sh -spgr <SG-name></code>
Output directory	<code>run_autoSHARP.sh -id <output></code>
Skip automatic model building	<code>run_autoSHARP.sh -nobuild</code>
Examples	
SAD (Se-MET)	<code>run_autoSHARP.sh -seq 1o22.pir \ -ha "Se" \ -wvl 0.9778 peak -7 5 -sca 1o22_peak.sca</code>
MAD (2-wavelength Se-MET)	<code>run_autoSHARP.sh -seq 3isy.pir \ -ha Se \ -wvl 0.97934 infl -11 3.3 -sca aimless_0.97934A.sca \ -wvl 0.91162 hrem -1.8 3.3 -sca aimless_0.91162A.sca</code>
SIR(AS) (mercury derivative)	<code>run_autoSHARP.sh -seq 1GXT.pir \ -nat -mtz 1GXT_nat.mtz \ -ha Hg -nsit 2 \ -wvl 0.99970 peak -16 10 -mtz 1GXT_hg.mtz</code>
MIR(AS) (two derivatives)	<code>run_autoSHARP.sh -seq 3zft.pir \ -nat -mtz 3zft_nat.mtz \ -ha Hg -nsit 1 \ -wvl 1.54179 -mtz 3zfq_Hg.mtz \ -ha Ir -nsit 2 \ -wvl 1.54179 -mtz 3zfr_Ir.mtz</code>
Including partial model or initial MR solution (can be used for all situations)	<code>run_autoSHARP.sh -seq 3get.pir \ -ha Se \ -pdb 3ffh_ala_MR.pdb \ -wvl 0.9789 peak -8 4 -sca 3get.sca</code>
SAD with Ta₆Br₁₂ cluster at Ta edge	<code>run_autoSHARP.sh -seq 4cv5.pir \ -ha "Ta6Br12:Ta" -nsit 1 \ -wvl 1.25472 peak -mtz 4cv5.mtz</code>

autoSHARP reference card	
Analysing output	
LLG residual maps (resid.mtz)	Columns for amplitude (* _F) and phase (* _P) are given. The naming conventions are: “* _HAT_* ” for the current heavy atom model and “* _RES_* ” for residual maps (to find new sites or adjust current model). The first 4 numbers correspond to the Compound-Crystal-Wavelength-Batch hierarchy of SHARP .
Initial experimental phases (eden.mtz)	Useful columns are: FP/SIGFP (unperturbed structure factor), HLA-D (Hendrickson-Lattmann coefficients), FB/PHIB or Fcent/PHIcent (purely experimental map, ie. before solvent flattening)
Solvent-flattened map (eden_flat_*pc.mtz)	Use columns FBshasol/PHIBshasol in Coot
Some useful commands	
Converting from PDB to fractional coordinates	coordconv xyzin some.pdb xyzout some.frc <<e INPU PDB OUTP FRAC e
Calculating difference Fourier maps	diff_fourier -h # from BUSTER package
See also:	http://www.globalphasing.com/sharp/ http://www.globalphasing.com/sharp/wiki/